viscpost.py – Module for post-processing viscosity data

import viscpost as vp

por c moopoot as rp		
vd = loadvisc(filename, ifplot=True)	load a visc_ file by file name (could be path)	ViscData
vd = readvisc('PEC6', 373,0.1,1e8,ifplot=True)	Load a visc_file by information	ViscData
vba = batch('PEC6',373,0.1)	Load a batch of visc_file and calculate the average and error	ViscBatch

Class ViscData

vd.material	PEC5 or PEC6	string
vd.temp	temperature [K]	string
vd.press	pressure [MPa]	string
vd.srate	shear rate [s-1], eg 1e+08	string
vd.dt	timestep [fs], =0.5	float
vd.step	step	Series
vd.time	time [ns]	Series
vd.strain	strain	Series
vd.visc	viscosity [mPa s]	Series
vd.sslength	length of steady steady [ns], = 20	int
vd.ssdata	steady-state data	DataFrame
vd.outputreq	output frequency, = 100000	int

s = vd.info(ifprint=True)	return 'PEC5, 340K, 50MPa, 1e+08 1/s'
vd.plot(window=50)	plot for all the data
vd.ssplot(window=50)	plot only for the steady-state data
vd.acf(data=None,Nblock=4,lags=50)	perform autocorrelation analysis
vd.setss(ts)	set steady-state starting at ts [ns]
vd.setss1(t_begin,t_end)	set steady-state from to
mean, error = vd.average(blocknum = 10)	perform block average

Class BatchData

vba.material	PEC5 or PEC	PEC5 or PEC6	
vba.temp	temperature	temperature [K]	
vba.press	pressure [MF	pressure [MPa]	
vba.srate	shear rate [s-	shear rate [s-1], eg 1e+08	
vba.visclist	ViscData obe	ViscData obejcts for various sheat rates	
vba.results		a table of viscosity average and error for various shear rates. Columns: srate, mean, erorr, relative error	
vd = vba.get(srate)		retrieve the ViscData via the corresponding strain rate as the key	ViscData
vba.plot(model=Eyring,color='b', xlim=(1e6,1e11),ylim=(1,100)		plot viscosity vs. shear rate fit the data to a model (Eyring by default)	-
vba.axplot(ax,same as above)		for multiple plots (also returns optimized parameters and the parameter standard errors)	[eta_N,error*], [sigma_E,error], ax
vba.plotall()		plot viscosity vs. time for all shear rates	

vba.fit(model)	fit results to a model (Eyring, Carreau)	popt: array per*: array *standard error
vba.export()	export the results to a file (.nemd) for the use of OriginLab plot	
vba.print()	print results to screen	

Impoutpost.py – Module for post-processing general LAMMPS outputs

import Impoutpost as Imp

df = loadvisc(filename)	load a visc_ file by file name (could be path)	DataFrame
<pre>plot(df,dt=0.5, title=None,window=100)</pre>	general plot, capable of multiple variables	-
<pre>plot1(df,dt=0.5,title=None, window=100,sharex=True):</pre>	plot a single varial against time	fig, ax
blockACF(df,Nblock=4,lags=50, t0=0.5,outputfreq=100000)	perform a block analysis	-
mean, expanderror = blockAverage(df,b,style='blocknum'):	perform block average. b is block number or block size depending style = 'blocknum' or 'blocksize'	float, float
<pre>blockSizing(df, isplot=True, maxBlockSize=0):</pre>	compute block average & error for varied sizes	-

utility.py — Module for quick visualizing and handling lammps output Automatically run at startup of Jupyter Lab

plot(filename)	vba=	copy()
	analyze(material,temp,press)	

General workflow

- 1. Use the scripts in /lmpscript to run equilbration and NEMD simulations using LAMMPS on a HPC server.
- 2. When computation completed, download the files from the server to: ./data/new.
- 3. Open a iPython-like terminal or a Juypter notebook, cd to ./data/new, import the modules in /src to post-process and analyze the data. Here are some tips:
 - Use vba = analyze() to quick-check all the viscosity output files in ./data/new. vba is a BatchData class
 that has a bunch of useful functions you can play with to analyze the viscosity data.
 - Use plot('filename') to visualize the output files that compute pressure, energy, etc. as a function of time. This is primarily to check if the equilibration or steady state is reached.
 - Use vd = vba.get(srate) to quickly retrieve a dataset for a state point where srate is the shear rate (1/s), e.g, 1e8, 1e9. vd is a ViscData class that also has a bunch of useful functions for analysis.
 - Deep steady-state check: use vd.acf(), vd.ssplot(), vd.setss1(), etc
- 4. If steady-state is reached and desired statistical accuracy has been achieved, run copy('MaterialName') to copy the visc_ file to the ./data/visc. Move all files in ./data/new to ./data/archive. Otherwise go back to LAMMPS for longer simulation until obtaining the desired results.
- 5. Create a Jupyter notebook to do analysis and write report using the modules in ./src and the data in ./data/visc. Export results if necessary for publication and making figures using other software..

Some default values:

- > temp, press
- > t0=0.5, outputfreg=100000
- > #block=10. To change, go to viscpost->ViscData->def average